




POP EMAIL ACCOUNT SETUP



1. Open the Android Applications menu and select the **Email** icon.




2. Select **Menu** -> select **Accounts** -> then **Add Account**.
 - Enter your account information:
 - Email address**: your full email address
 - Password**: your password
 - Select **Manual setup**.



3. Choose **POP3 account**.

POP EMAIL ACCOUNT SETUP (cont.)




The screenshot shows the 'Incoming server settings' screen. It has a dark background with white text and input fields. At the top, the status bar shows 92% battery, signal strength, and the time 1:35 PM. The settings are as follows:

- User name: John@example.com
- Password: [Redacted]
- POP3 server: pop.emailhosting.com
- Port: 110
- Security type: None
- Delete email from server: Never

A 'Next' button is at the bottom.

- Complete these **Incoming server settings**:
 - Username** is your full email address
 - Password** is your password
 - POP3 server** is pop.emailhosting.com
 - Port** for POP3 is **110**.
 - Security type** is **None**
 - Select **Next**.




The screenshot shows the 'Outgoing server settings' screen. It has a dark background with white text and input fields. At the top, the status bar shows 87% battery, signal strength, and the time 10:12 AM. The settings are as follows:

- SMTP server: smtp.emailhosting.com
- Port: 2500
- Security type: None
- Require sign-in
- User name: John@example.com
- Password: [Redacted]

A 'Next' button is at the bottom.

- Enter your outgoing server settings.
 - SMTP server** name is smtp.emailhosting.com
 - Outgoing **port** is **2500**
 - Security type** is **None**
 - Select/check the **Require sign-in** box
 - Username** is your full email address
 - Password** is your password
 - Select **Next**.



The screenshot shows the 'Account options' screen. It has a dark background with white text and a dropdown menu. At the top, the status bar shows 87% battery, signal strength, and the time 10:12 AM. The settings are as follows:

- Email check frequency: Every 30 minutes
- Send email from this account by default
- Notify me when email arrives

A 'Next' button is at the bottom.

- Select how often you would to check for new email and select **Next**.

➤ POP EMAIL ACCOUNT SETUP (cont.)



7. Type the name you would like to have appear on outgoing messages, then select **Done**. 🌐

NOTE: As a courtesy, we provide information about how to use certain third-party products but we do not endorse or directly support third-party products, and we are not responsible for the functions or reliability of such products. Google™ Android is a registered trademark of Google in the United States and/or other countries. All rights reserved.